

VOMS C API Reference Manual

1.5.0

Generated by Doxygen 1.2.14

Thu Jan 29 11:36:24 2004

Contents

1	VOMS C API Data Structure Index	1
1.1	VOMS C API Data Structures	1
2	VOMS C API File Index	3
2.1	VOMS C API File List	3
3	VOMS C API Data Structure Documentation	5
3.1	contactdata Struct Reference	5
3.2	data Struct Reference	7
3.3	voms Struct Reference	8
3.4	vomsdata Struct Reference	11
4	VOMS C API File Documentation	13
4.1	voms_apic.h File Reference	13

Chapter 1

VOMS C API Data Structure Index

1.1 VOMS C API Data Structures

Here are the data structures with brief descriptions:

<code>contactdata</code>	5
<code>data</code> (User's characteristics: can be repeated)	7
<code>voms</code>	8
<code>vomsdata</code>	11

Chapter 2

VOMS C API File Index

2.1 VOMS C API File List

Here is a list of all files with brief descriptions:

voms_apic.h	13
-----------------------	----

Chapter 3

VOMS C API Data Structure Documentation

3.1 contactdata Struct Reference

```
#include <voms_apic.h>
```

Data Fields

- char * `nick`
- char * `host`
- char * `contact`
- char * `vo`
- int `port`
- char * `reserved`

3.1.1 Field Documentation

3.1.1.1 char* contactdata::contact

The subject of the server's certificate

Definition at line 37 of file voms_apic.h.

3.1.1.2 char* contactdata::host

The hostname of the server

Definition at line 36 of file voms_apic.h.

3.1.1.3 char* contactdata::nick

The alias of the server

Definition at line 35 of file voms_apic.h.

3.1.1.4 int contactdata::port

The port on which the server is listening

Definition at line 39 of file voms_apic.h.

3.1.1.5 char* contactdata::reserved

HANDS OFF!

Definition at line 40 of file voms_apic.h.

3.1.1.6 char* contactdata::vo

The VO served by this server

Definition at line 38 of file voms_apic.h.

The documentation for this struct was generated from the following file:

- [voms_apic.h](#)

3.2 data Struct Reference

User's characteristics: can be repeated.

```
#include <voms_apic.h>
```

Data Fields

- char * [group](#)
- char * [role](#)
- char * [cap](#)

3.2.1 Detailed Description

User's characteristics: can be repeated.

Definition at line 25 of file voms_apic.h.

3.2.2 Field Documentation

3.2.2.1 char* data::cap

user's capability

Definition at line 28 of file voms_apic.h.

3.2.2.2 char* data::group

user's group

Definition at line 26 of file voms_apic.h.

3.2.2.3 char* data::role

user's role

Definition at line 27 of file voms_apic.h.

The documentation for this struct was generated from the following file:

- [voms_apic.h](#)

3.3 voms Struct Reference

```
#include <voms_apic.h>
```

Data Fields

- int **siglen**
- char * **signature**
- char * **user**
- char * **userca**
- char * **server**
- char * **serverca**
- char * **voname**
- char * **uri**
- char * **date1**
- char * **date2**
- int **type**
- **data ** std**
- char * **custom**
- int **datalen**
- int **version**
- char ** **fqan**
- char * **serial**

3.3.1 Field Documentation

3.3.1.1 **char* voms::custom**

The **data** returned by an S command

Definition at line 64 of file voms_apic.h.

3.3.1.2 **int voms::datalen**

Definition at line 65 of file voms_apic.h.

3.3.1.3 **char* voms::date1**

Beginning of validity of the user info

Definition at line 60 of file voms_apic.h.

3.3.1.4 **char* voms::date2**

End of validity of the user info

Definition at line 61 of file voms_apic.h.

3.3.1.5 char voms::fqan**

User's attributes in compact format

Definition at line 67 of file voms_apic.h.

3.3.1.6 char* voms::serial

Serial number. Only significant if coming from AC. Null otherwise

Definition at line 68 of file voms_apic.h.

3.3.1.7 char* voms::server

The VOMS server DN, as from its certificate

Definition at line 56 of file voms_apic.h.

3.3.1.8 char* voms::serverca

The CA which signed the VOMS certificate

Definition at line 57 of file voms_apic.h.

3.3.1.9 int voms::siglen

The length of the VOMS server signature

Definition at line 52 of file voms_apic.h.

3.3.1.10 char* voms::signature

The VOMS server signature

Definition at line 53 of file voms_apic.h.

3.3.1.11 struct data voms::std**

User's characteristics

Definition at line 63 of file voms_apic.h.

3.3.1.12 int voms::type

The type of **data** returned

Definition at line 62 of file voms_apic.h.

3.3.1.13 char* voms::uri

The URI of the VOMS server

Definition at line 59 of file voms_apic.h.

3.3.1.14 char* voms::user

The user's DN, as from his certificate

Definition at line 54 of file voms_apic.h.

3.3.1.15 char* voms::userca

The CA which signed the user's certificate

Definition at line 55 of file voms_apic.h.

3.3.1.16 int voms::version

Definition at line 66 of file voms_apic.h.

3.3.1.17 char* voms::voname

The name of the VO to which the VOMS belongs

Definition at line 58 of file voms_apic.h.

The documentation for this struct was generated from the following file:

- [voms_apic.h](#)

3.4 vomsdata Struct Reference

```
#include <voms_apic.h>
```

Data Fields

- `char * cdir`
- `char * vdir`
- `voms ** data`
- `char * workvo`
- `char * extra_data`
- `int volen`
- `int extralen`

3.4.1 Field Documentation

3.4.1.1 `char* vomsdata::cdir`

Definition at line 113 of file voms_apic.h.

3.4.1.2 `struct voms** vomsdata::data`

User's info, as in the certificate extension. It may contain `data` gathered from more than one VOMS server,
Definition at line 115 of file voms_apic.h.

3.4.1.3 `char* vomsdata::extra_data`

The `data` specified by the user with the `-include` switch. Note that this field doesn't contain the result of a request to the VOMS server, but instead `data` specified by the user. The reason for the introduction of this extension is to let a user include important `data` into his proxy certificate, like, for example, a kerberos ticket

Definition at line 120 of file voms_apic.h.

3.4.1.4 `int vomsdata::extralen`

Definition at line 130 of file voms_apic.h.

3.4.1.5 `char* vomsdata::vdir`

Definition at line 114 of file voms_apic.h.

3.4.1.6 `int vomsdata::volen`

Definition at line 129 of file voms_apic.h.

3.4.1.7 char* vomsdata::workvo

The value of the -vo option of the [voms-proxy-init](#) command

Definition at line 118 of file [voms_apic.h](#).

The documentation for this struct was generated from the following file:

- [voms_apic.h](#)

Chapter 4

VOMS C API File Documentation

4.1 voms_apic.h File Reference

```
#include <openssl/x509.h>
```

Data Structures

- struct `contactdata`
- struct `data`

User's characteristics: can be repeated.

- struct `voms`
- struct `vomsdata`

Defines

- #define `TYPE_NODATA` 0 /*!< no `data` */

The type of `data` returned.

- #define `TYPE_STD` 1 /*!< group, role, capability triplet */
- #define `TYPE_CUSTOM` 2 /*!< result of an S command */
- #define `RECURSE_CHAIN` 0
- #define `RECURSE_NONE` 1
- #define `VERIFY_FULL` 0xffffffff
- #define `VERIFY_NONE` 0x00000000
- #define `VERIFY_DATE` 0x00000001
- #define `VERIFY_NOTARGET` 0x00000002
- #define `VERIFY_KEY` 0x00000004
- #define `VERIFY_SIGN` 0x00000008
- #define `VERIFY_ORDER` 0x00000010
- #define `VERIFY_ID` 0x00000020
- #define `VERR_NONE` 0

Error codes.

- #define **VERR_NOSOCKET** 1 /*!< Socket problem*/
- #define **VERR_NOIDENT** 2 /*!< Cannot identify itself (certificate problem) */
- #define **VERR_COMM** 3 /*!< Server problem */
- #define **VERR_PARAM** 4 /*!< Wrong parameters*/
- #define **VERR_NOEXT** 5 /*!< VOMS extension missing */
- #define **VERR_NOINIT** 6 /*!< Initialization error */
- #define **VERR_TIME** 7 /*!< Error in time checking */
- #define **VERR_IDCHECK** 8 /*!< User **data** in extension different from the real
- #define **VERR_EXTRAINFO** 9 /*!< VO name and URI missing */
- #define **VERR_FORMAT** 10 /*!< Wrong **data** format */
- #define **VERR_NODATA** 11 /*!< Empty extension */
- #define **VERR_PARSE** 12 /*!< Parse error */
- #define **VERR_DIR** 13 /*!< Directory error */
- #define **VERR_SIGN** 14 /*!< Signature error */
- #define **VERR_SERVER** 15 /*!< Unidentifiable VOMS server */
- #define **VERR_MEM** 16 /*!< Memory problems */
- #define **VERR_VERIFY** 17 /*!< Generic verification error*/
- #define **VERR_TYPE** 18 /*!< Returned **data** of unknown type */
- #define **VERR_ORDER** 19 /*!< Ordering different than required */
- #define **VERR_SERVERCODE** 20 /*!< Error from the server */

Functions

- **contactdata ** VOMS_FindByAlias** (struct **vomsdata** *vd, char *alias, char *system, char *user, int *error)
- **contactdata ** VOMS_FindByVO** (struct **vomsdata** *vd, char *vo, char *system, char *user, int *error)
- void **VOMS_DeleteContacts** (struct **contactdata** **list)
- **vomsdata * VOMS_Init** (char *voms, char *cert)
- **voms * VOMS_Copy** (struct **voms** *v, int *error)
- **vomsdata * VOMS_CopyAll** (struct **vomsdata** *vd, int *error)
- void **VOMS_Delete** (struct **voms** *v)
- int **VOMS_AddTarget** (struct **vomsdata** *vd, char *target, int *error)
- void **VOMS_FreeTargets** (struct **vomsdata** *vd, int *error)
- char * **VOMS_ListTargets** (struct **vomsdata** *vd, int *error)
- int **VOMS_SetVerificationType** (int type, struct **vomsdata** *vd, int *error)
- int **VOMS_SetLifetime** (int length, struct **vomsdata** *vd, int *error)
- void **VOMS_Destroy** (struct **vomsdata** *vd)
- int **VOMS_ResetOrder** (struct **vomsdata** *vd, int *error)
- int **VOMS_Ordering** (char *order, struct **vomsdata** *vd, int *error)
- int **VOMS_Contact** (char *hostname, int port, char *servsubject, char *command, struct **vomsdata** *vd, int *error)
- int **VOMS>ContactRaw** (char *hostname, int port, char *servsubject, char *command, void ****data**, int *datalen, int *version, struct **vomsdata** *vd, int *error)
- int **VOMS_Retrieve** (X509 *cert, STACK_OF(X509)*chain, int how, struct **vomsdata** *vd, int *error)
- int **VOMS_Import** (char *buffer, int buflen, struct **vomsdata** *vd, int *error)
- int **VOMS_Export** (char **buffer, int *buflen, struct **vomsdata** *vd, int *error)
- **voms * VOMS_DefaultData** (struct **vomsdata** *vd, int *error)
- int **getMajorVersionNumber** (void)
- int **getMinorVersionNumber** (void)
- int **getPatchVersionNumber** (void)

4.1.1 Define Documentation

4.1.1.1 #define RECURSE_CHAIN 0

Definition at line 74 of file voms_apic.h.

4.1.1.2 #define RECURSE_NONE 1

Definition at line 75 of file voms_apic.h.

4.1.1.3 #define TYPE_CUSTOM 2 /*!< result of an S command */

Definition at line 48 of file voms_apic.h.

4.1.1.4 #define TYPE_NODATA 0 /*!< no data */

The type of `data` returned.

Definition at line 46 of file voms_apic.h.

4.1.1.5 #define TYPE_STD 1 /*!< group, role, capability triplet */

Definition at line 47 of file voms_apic.h.

4.1.1.6 #define VERIFY_DATE 0x00000001

Definition at line 79 of file voms_apic.h.

4.1.1.7 #define VERIFY_FULL 0xffffffff

Definition at line 77 of file voms_apic.h.

4.1.1.8 #define VERIFY_ID 0x00000020

Definition at line 84 of file voms_apic.h.

4.1.1.9 #define VERIFY_KEY 0x00000004

Definition at line 81 of file voms_apic.h.

4.1.1.10 #define VERIFY_NONE 0x00000000

Definition at line 78 of file voms_apic.h.

4.1.1.11 #define VERIFY_NOTARGET 0x00000002

Definition at line 80 of file voms_apic.h.

4.1.1.12 #define VERIFY_ORDER 0x00000010

Definition at line 83 of file voms_apic.h.

4.1.1.13 #define VERIFY_SIGN 0x00000008

Definition at line 82 of file voms_apic.h.

4.1.1.14 #define VERR_COMM 3 /*!< Server problem */

Definition at line 92 of file voms_apic.h.

4.1.1.15 #define VERR_DIR 13 /*!< Directory error */

Definition at line 103 of file voms_apic.h.

4.1.1.16 #define VERR_EXTRAINFO 9 /*!< VO name and URI missing */

Definition at line 99 of file voms_apic.h.

4.1.1.17 #define VERR_FORMAT 10 /*!< Wrong **data format */**

Definition at line 100 of file voms_apic.h.

4.1.1.18 #define VERR_IDCHECK 8 /*!< User **data in extension different from the real**

Definition at line 97 of file voms_apic.h.

4.1.1.19 #define VERR_MEM 16 /*!< Memory problems */

Definition at line 106 of file voms_apic.h.

4.1.1.20 #define VERR_NODATA 11 /*!< Empty extension */

Definition at line 101 of file voms_apic.h.

4.1.1.21 #define VERR_NOEXT 5 /*!< VOMS extension missing */

Definition at line 94 of file voms_apic.h.

4.1.1.22 #define VERR_NOIDENT 2 /*!< Cannot identify itself (certificate problem) */

Definition at line 91 of file voms_apic.h.

4.1.1.23 #define VERR_NOINIT 6 /*!< Initialization error */

Definition at line 95 of file voms_apic.h.

4.1.1.24 #define VERR_NONE 0

Error codes.

Definition at line 89 of file voms_apic.h.

4.1.1.25 #define VERR_NOSOCKET 1 /*!< Socket problem*/

Definition at line 90 of file voms_apic.h.

4.1.1.26 #define VERR_ORDER 19 /*!< Ordering different than required */

Definition at line 109 of file voms_apic.h.

4.1.1.27 #define VERR_PARAM 4 /*!< Wrong parameters*/

Definition at line 93 of file voms_apic.h.

4.1.1.28 #define VERR_PARSE 12 /*!< Parse error */

Definition at line 102 of file voms_apic.h.

4.1.1.29 #define VERR_SERVER 15 /*!< Unidentifiable VOMS server */

Definition at line 105 of file voms_apic.h.

4.1.1.30 #define VERR_SERVERCODE 20 /*!< Error from the server */

Definition at line 110 of file voms_apic.h.

4.1.1.31 #define VERR_SIGN 14 /*!< Signature error */

Definition at line 104 of file voms_apic.h.

4.1.1.32 #define VERR_TIME 7 /*!< Error in time checking */

Definition at line 96 of file voms_apic.h.

4.1.1.33 #define VERR_TYPE 18 /*!< Returned **data of unknown type */**

Definition at line 108 of file voms_apic.h.

4.1.1.34 #define VERR_VERIFY 17 /*!< Generic verification error*/

Definition at line 107 of file voms_apic.h.

4.1.2 Function Documentation

4.1.2.1 int getMajorVersionNumber (void)**4.1.2.2 int getMinorVersionNumber (void)****4.1.2.3 int getPatchVersionNumber (void)****4.1.2.4 int VOMS_AddTarget (struct vomsdata * *vd*, char * *target*, int * *error*)**

Adds a target to the AC.

Parameters:

vd The [vomsdata](#) structure.

target The target to add. It should be a FQDN.

error RETURN PARAMETER: qualifies the error message.

Returns:

failure (0) or success (<>0)

4.1.2.5 int VOMS_Contact (char * *hostname*, int *port*, char * *servsubject*, char * *command*, struct vomsdata * *vd*, int * *error*)

Contacts a VOMS server to get a certificate

It is the equivalent of the `voms_proxy_init` command, but without the `--include` functionality.

Parameters:

hostname FQDN of the VOMS server

port the port on which the VOMS server is listening

servsubject the subject of the server's certificate

command Command

vd RETURN PARAMETER: contains the [data](#) returned by the connection

error RETURN PARAMETER: Qualifies the error message

Returns:

failure (0) or success (<>0)

4.1.2.6 int VOMS_ContactRaw (char * *hostname*, int *port*, char * *servsubject*, char * *command*, void ** *data*, int * *datalen*, int * *version*, struct vomsdata * *vd*, int * *error*)

The same as `VOMS_Contact`, except that instead of starting the verification process, the [data](#) is returned as is in the

Parameters:

data and

datalen fields.

version is the version number of the *data*.

4.1.2.7 struct voms* VOMS_Copy (struct voms * *v*, int * *error*)

Copies a *voms* structure. N.B: This is the ONLY way to correctly initialize a *voms* structure.

Parameters:

v The structure to copy.

error RETURN PARAMETER: qualifies the error message.

Returns:

NULL (error) or the new *voms* structure.

4.1.2.8 struct vomsdata* VOMS_CopyAll (struct vomsdata * *vd*, int * *error*)

Copies a *vomsdata* structure. N.B: This is the ONLY way to correctly initialize a *vomsdata* structure.

Parameters:

vd The structure to copy.

error RETURN PARAMETER: qualifies the error message.

Returns:

NULL (error) or the new *vomsdata* structure.

4.1.2.9 struct voms* VOMS_DefaultData (struct vomsdata * *vd*, int * *error*)

Gets the default attributes from a *vomsdata* structure.

Parameters:

vd the *vomsdata* structure to analyze

error RETURN PARAMETER: Qualifies the error message

Returns:

a pointer to the relevant *voms* structure. DO NOT modify the fields.

4.1.2.10 void VOMS_Delete (struct voms * *v*)

Deletes a *voms* structure

Parameters:

v Pointer to the structure to delete.

4.1.2.11 void VOMS_DeleteContacts (struct contactdata ** *list*)

Frees a `contactdata` vector.

Parameters:

list The vector to free.

Returns:

NONE

4.1.2.12 void VOMS_Destroy (struct vomsdata * *vd*)

Destroys a proper `vomsdata` structure /param vd The structure to deallocate.

4.1.2.13 int VOMS_Export (char ** *buffer*, int * *buflen*, struct vomsdata * *vd*, int * *error*)

4.1.2.14 struct contactdata** VOMS_FindByAlias (struct vomsdata * *vd*, char * *alias*, char * *system*, char * *user*, int * *error*)

Gets a list of VOMS servers which share an alias.

Parameters:

vd The correctly initialized `vomsdata` structured.

alias The alias to look for.

system The directory in which to look for the system configuration files. If NULL, defaults to /opt/edc/etc/vomses

user The directory in which to look for the user configuration files. Defaults to \$VOMS_USERCONF if NULL. Again defaults to \$HOME/.edg/vomses if the latter is NULL, or to ~/.edg/vomses as a last resort.

error RETURN PARAMETER: qualifies the error message.

Returns:

NULL, or a NULL-terminated vector of `contactdata` structures. The only supported way to free this array is via the `VOMS_DeleteContacts` function. Note also that the order in which the servers are returned is unspecified.

4.1.2.15 struct contactdata** VOMS_FindByVO (struct vomsdata * *vd*, char * *vo*, char * *system*, char * *user*, int * *error*)

Gets a list of VOMS servers which serve the same VO.

Parameters:

vd The correctly initialized `vomsdata` structured.

vo The VO to look for.

system The directory in which to look for the system configuration files. If NULL, defaults to /opt/edc/etc/vomses

user The directory in which to look for the user configuration files. Defaults to \$VOMS_USERCONF if NULL. Again defaults to \$HOME/.edg/vomses if the latter is NULL, or to ~/.edg/vomses as a last resort.

error RETURN PARAMETER: qualifies the error message.

Returns:

NULL, or a NULL-terminated vector of [contactdata](#) structures. The only supported way to free this array is via the VOMS_DeleteContacts function. Note also that the order in which the servers are returned is unspecified.

4.1.2.16 void VOMS_FreeTargets (struct [vomsdata](#) * *vd*, int * *error*)

Delete the targets from the AC.

Parameters:

vd The [vomsdata](#) structure.

error RETURN PARAMETER: qualifies the error message.

4.1.2.17 int VOMS_Import (char * *buffer*, int *buflen*, struct [vomsdata](#) * *vd*, int * *error*)

Converts [data](#) from the format used for inclusion into a certificate to the internal format

The function does verify the [data](#).

Parameters:

buffer contains the [data](#) to be converted

buflen contains the length of buffer

vd RETURN PARAMETER: contains the [data](#) returned by the connection

error RETURN PARAMETER: Qualifies the error message

Returns:

failure (0) or success (<>0)

4.1.2.18 struct [vomsdata](#)* VOMS_Init (char * *voms*, char * *cert*)

Initializes a [vomsdata](#) structure for use by the other functions. N.B: This is the ONLY way to correctly initialize a [vomsdata](#) structure. It is also forbidden to directly take the sizeof() of this structure.

Parameters:

voms The directory which contains the certificates of the VOMS servers

cert The directory which contains the CA certificates

If voms_dir is empty, the value of the environment variable X509_VOMS_DIR is taken

If cert_dir is empty, the value of the environment variable X509_CERT_DIR is taken

Returns:

NULL for failure, or a pointer to a properly initialized structure.

4.1.2.19 char* VOMS_ListTargets (struct vomsdata * *vd*, int * *error*)**4.1.2.20 int VOMS_Ordering (char * *order*, struct vomsdata * *vd*, int * *error*)**

Further specified the order of the returned attributes. Please do note that calls are cumulative unless `VOMS_ResetOrder()` is called.

Parameters:

order the group:role attribute.

vd RETURN PARAMETER: contains the modified `data`.

error RETURN PARAMETER: Qualifies the error message

Returns:

failure (0) or success (<>0)

4.1.2.21 int VOMS_ResetOrder (struct vomsdata * *vd*, int * *error*)

Unsets the return order of the attributes.

Parameters:

vd RETURN PARAMETER: contains the modified `data`.

error RETURN PARAMETER: Qualifies the error message

Returns:

failure (0) or success (<>0)

4.1.2.22 int VOMS_Retrieve (X509 * *cert*, STACK_OF(X509)* *chain*, int *how*, struct vomsdata * *vd*, int * *error*)

Extracts the VOMS extension from an X.509 certificate.

The function doesn't check the validity of the certificates, but it does check the content of the user `data`.

Parameters:

cert The certificate with the VOMS extensions

chain The chain of the validation certificates (only the intermediate ones)

how Recursion type

vd RETURN PARAMETER: contains the `data` returned by the connection

error RETURN PARAMETER: Qualifies the error message

Returns:

failure (0) or success (<>0)

4.1.2.23 int VOMS_SetLifetime (int *length*, struct vomsdata * *vd*, int * *error*)

Set requested lifetime for `VOMS>Contact()` calls.

Parameters:

length Lifetime requested.

vd RETURN PARAMETER: contains the modified [data](#).

error RETURN PARAMETER: Qualifies the error message

Returns:

failure (0) or success (<>0)

4.1.2.24 int VOMS_SetVerificationType (int *type*, struct [vomsdata](#) * *vd*, int * *error*)

Index

cap contactdata, 5
 data, 7
cdir nick
 vomsdata, 11
contact contactdata, 5
contactdata, 5
 contact, 5
 host, 5
 nick, 5
 port, 5
 reserved, 6
 vo, 6
custom voms, 8
data, 7
 cap, 7
 group, 7
 role, 7
 vomsdata, 11
datalen voms, 8
date1 voms, 8
date2 voms, 8
extra_data vomsdata, 11
extralen vomsdata, 11
fqan voms, 8
getMajorVersionNumber voms_apic.h, 18
getMinorVersionNumber voms_apic.h, 18
getPatchVersionNumber voms_apic.h, 18
group data, 7
host contactdata, 5
 nick
 port
 RECURSE_CHAIN
 voms_apic.h, 15
 RECURSE_NONE
 voms_apic.h, 15
 reserved
 contactdata, 6
 role
 data, 7
 serial
 voms, 9
server voms, 9
serverca voms, 9
siglen voms, 9
signature voms, 9
std voms, 9
type voms, 9
 TYPE_CUSTOM
 voms_apic.h, 15
 TYPE_NODATA
 voms_apic.h, 15
 TYPE_STD
 voms_apic.h, 15
uri voms, 9
user voms, 9
userca voms, 10

vdir
 vomsdata, 11

VERIFY_DATE
 voms_apic.h, 15

VERIFY_FULL
 voms_apic.h, 15

VERIFY_ID
 voms_apic.h, 15

VERIFY_KEY
 voms_apic.h, 15

VERIFY_NONE
 voms_apic.h, 15

VERIFY_NOTARGET
 voms_apic.h, 15

VERIFY_ORDER
 voms_apic.h, 15

VERIFY_SIGN
 voms_apic.h, 16

VERR_COMM
 voms_apic.h, 16

VERR_DIR
 voms_apic.h, 16

VERR_EXTRAINFO
 voms_apic.h, 16

VERR_FORMAT
 voms_apic.h, 16

VERR_IDCHECK
 voms_apic.h, 16

VERR_MEM
 voms_apic.h, 16

VERR_NODATA
 voms_apic.h, 16

VERR_NOEXT
 voms_apic.h, 16

VERR_NOIDENT
 voms_apic.h, 16

VERR_NOINIT
 voms_apic.h, 16

VERR_NONE
 voms_apic.h, 17

VERR_NOSOCKET
 voms_apic.h, 17

VERR_ORDER
 voms_apic.h, 17

VERR_PARAM
 voms_apic.h, 17

VERR_PARSE
 voms_apic.h, 17

VERR_SERVER
 voms_apic.h, 17

VERR_SERVERCODE
 voms_apic.h, 17

VERR_SIGN
 voms_apic.h, 17

VERR_TIME
 voms_apic.h, 17

VERR_TYPE
 voms_apic.h, 17

VERR_VERIFY
 voms_apic.h, 17

version
 voms, 10

vo
 contactdata, 6

volen
 vomsdata, 11

voms, 8
 custom, 8
 datalen, 8
 date1, 8
 date2, 8
 fqan, 8
 serial, 9
 server, 9
 serverca, 9
 siglen, 9
 signature, 9
 std, 9
 type, 9
 uri, 9
 user, 9
 userca, 10
 version, 10
 voname, 10

VOMS_AddTarget
 voms_apic.h, 18

voms_apic.h, 13
 getMajorVersionNumber, 18
 getMinorVersionNumber, 18
 getPatchVersionNumber, 18

RECURSE_CHAIN, 15

RECURSE_NONE, 15

TYPE_CUSTOM, 15

TYPE_NODATA, 15

TYPE_STD, 15

VERIFY_DATE, 15

VERIFY_FULL, 15

VERIFY_ID, 15

VERIFY_KEY, 15

VERIFY_NONE, 15

VERIFY_NOTARGET, 15

VERIFY_ORDER, 15

VERIFY_SIGN, 16

VERR_COMM, 16

VERR_DIR, 16

VERR_EXTRAINFO, 16

VERR_FORMAT, 16

VERR_IDCHECK, 16

VERR_MEM, 16
 VERR_NODATA, 16
 VERR_NOEXT, 16
 VERR_NOIDENT, 16
 VERR_NOINIT, 16
 VERR_NONE, 17
 VERR_NOSOCKET, 17
 VERR_ORDER, 17
 VERR_PARAM, 17
 VERR_PARSE, 17
 VERR_SERVER, 17
 VERR_SERVERCODE, 17
 VERR_SIGN, 17
 VERR_TIME, 17
 VERR_TYPE, 17
 VERR_VERIFY, 17
 VOMS_AddTarget, 18
 VOMS_Contact, 18
 VOMS_ContactRaw, 18
 VOMS_Copy, 19
 VOMS_CopyAll, 19
 VOMS_DefaultData, 19
 VOMS_Delete, 19
 VOMS_DeleteContacts, 19
 VOMS_Destroy, 20
 VOMS_Export, 20
 VOMS_FindByAlias, 20
 VOMS_FindByVO, 20
 VOMS_FreeTargets, 21
 VOMS_Import, 21
 VOMS_Init, 21
 VOMS_ListTargets, 21
 VOMS_Ordering, 22
 VOMS_ResetOrder, 22
 VOMS_Retrieve, 22
 VOMS_SetLifetime, 22
 VOMS_SetVerificationType, 23
 VOMS>Contact
 voms_apic.h, 18
 VOMS>ContactRaw
 voms_apic.h, 18
 VOMS_Copy
 voms_apic.h, 19
 VOMS_CopyAll
 voms_apic.h, 19
 VOMS_DefaultData
 voms_apic.h, 19
 VOMS_Delete
 voms_apic.h, 19
 VOMS_DeleteContacts
 voms_apic.h, 19
 VOMS_Destroy
 voms_apic.h, 20
 VOMS_Export
 voms_apic.h, 20
 VOMS_FindByAlias
 voms_apic.h, 20
 VOMS_FindByVO
 voms_apic.h, 20
 VOMS_FreeTargets
 voms_apic.h, 21
 VOMS_Import
 voms_apic.h, 21
 VOMS_Init
 voms_apic.h, 21
 VOMS>ListTargets
 voms_apic.h, 21
 VOMS_Ordering
 voms_apic.h, 22
 VOMS_ResetOrder
 voms_apic.h, 22
 VOMS_Retrieve
 voms_apic.h, 22
 VOMS_SetLifetime
 voms_apic.h, 22
 VOMS_SetVerificationType
 voms_apic.h, 23
 vomsdata, 11
 cdir, 11
 data, 11
 extra_data, 11
 extralen, 11
 vdir, 11
 voLEN, 11
 workvo, 11
 voname
 voms, 10
 workvo
 vomsdata, 11